

Slides, videos, links and more:

<https://github.com/physicell-training/ws2023>


Setting up PhysiCell on Linux

Elmar Bucher

 @MathCancer

PhysiCell Project

July 2023



LUDDY

SCHOOL OF INFORMATICS, COMPUTING, AND ENGINEERING

PhysiCell Project

PhysiCell.org

 @PhysiCell

Overview

This document describes the PhysiCell installation on a Debian Linux distribution. If you run on another flavor, please adjust accordingly.

- GCC
- ImageMagick, FFmpeg
- Git (optional)
- PhysiCell

} Minimum
Setup

-
- Python3 (miniconda), iPython, PhysiCell DataLoader
 - Jupyter (optional)
 - PhysiCell Studio

} Modeler
Setup

-
- Copasi

} Hackathon
Setup



LUDDY

SCHOOL OF INFORMATICS, COMPUTING, AND ENGINEERING

PhysiCell Project

PhysiCell.org

 **@PhysiCell**

GCC (Minimum Setup)

- check if GCC (the gnu compiler collection) is already installed
`g++ --version`
- if not:
`sudo apt install build-essential`
- OpenMP (open multi processing) is a feature, used by PhysiCell, that is implemented in GCC.



LUDDY

SCHOOL OF INFORMATICS, COMPUTING, AND ENGINEERING

PhysiCell Project

PhysiCell.org

 **@PhysiCell**

ImageMagick (Minimum Setup)

ImageMagick is used for making jpeg and gif images from PhysiCell svg image output.

- check if ImageMagick is already installed.
`magick --version`
 - if ok: wow, you have \geq version 7 installed. you are all set!
 - if you receive: Command 'magick' not found try:
`convert --version`
if ok: you have most probably a version 6 installed, like the most of us!
- if both of these commands not worked:
`sudo apt install imagemagick`
- the PhysiCell Makefile is written for ImageMagick \geq version 7, which requires a `magick` command in front of each ImageMagick command (e.g. `magick convert` instead of `convert`).

you can use sed to fix the Makefiles:

```
sed -i -e 's/magick //g' Makefile
```

`-i`: inplace `-e`: script expression `s`: substitute `g`: global

FFmpeg (Minimum Setup)

FFmpeg is used for making mp4 movies out of jpeg images.

- check if FFmpeg is already installed.

```
ffmpeg -version
```

- if not:

```
sudo apt install ffmpeg
```



LUDDY

SCHOOL OF INFORMATICS, COMPUTING, AND ENGINEERING

PhysiCell Project

PhysiCell.org

 **@PhysiCell**

Git (optional, Minimum Setup)

git is an alternative way to install the PhysiCell and the Studio source code. The common way is to use wget.

- check if git is already installed

```
git --version
```

- if not:

```
sudo apt install git
```

wget & unzip

Check if you have `wget` and `unzip` installed.

- `wget --version`
if not:
`sudo apt install wget`
- `unzip`
if not:
`sudo apt install unzip`

PhysiCell (Minimum Setup)

Download PhysiCell and place it where you want to work with this source code.

- **Git:**

```
git clone git@github.com:MathCancer/PhysiCell.git
```

- **Wget:**

```
wget https://github.com/MathCancer/PhysiCell/releases/download/1.12.0/PhysiCell\_V.1.12.0.zip  
unzip PhysiCell_V.1.12.0.zip
```

Test the installation with the biorobots sample project.

```
cd PhysiCell  
make biorobots-sample  
make  
./biorobots  
sed -i -e 's/magick //g' Makefile  
make jpeg  
make movie
```


Overview

This document describes the PhysiCell installation on a Debian Linux distribution. If you run on another flavor, please adjust accordingly.

- GCC
- ImageMagick, FFmpeg
- Git (optional)
- PhysiCell

} Minimum
Setup

-
- Python3 (miniconda), iPython, PhysiCell DataLoader
 - Jupyter (optional)
 - PhysiCell Studio

} Modeler
Setup

-
- Copasi

} Hackathon
Setup



Python3 part I (Modeler Setup)

It is up to you to use the python3 that ships with the distribution. The miniconda python3 distribution comes in handy, when you want to run somewhere python3 where you have no root rights.

- `cd` to the folder where you have your manual installed programs.
e.g. `~/local/lib/`
- adjust the download according to your CPU architecture (here x86_64)!
<https://conda.io/en/latest/miniconda.html>

```
wget https://repo.anaconda.com/miniconda/Miniconda3-py310\_23.3.1-0-Linux-x86\_64.sh  
chmod 775 Miniconda3-py310_23.3.1-0-Linux-x86_64.sh  
./Miniconda3-py310_23.3.1-0-Linux-x86_64.sh
```

- adjust the installation location to where your manual installed programs are.
e.g. `~/local/lib/miniconda3`
- you wish the installer to initialize Miniconda3!
`yes`
`source ~/.bashrc` (or log out and in again).

Python3 part 2 (Modeler Setup)

- The (base) environment should now be activated.
Check if the python and pip paths point to the installed location

```
which python  
which pip
```

- Install the iPython shell:
`pip install ipython`
- Install the PhysiCell DataLoader:
`pip install pcdl`
- Optional: install Jupyter:
`pip install jupyterlab`

PhysiCell Studio (Modeler Setup)

Download the studio and place it where you want to work with this source code.

- **Git:**

```
git clone git@github.com:PhysiCell-Tools/PhysiCell-Studio.git
```

- **Wget:**

```
wget https://github.com/PhysiCell-Tools/PhysiCell-Studio/archive/refs/tags/v2.26.7.zip  
unzip v2.26.7.zip
```

Put the studio under the PATH:

```
cd to the folder where you have your manual installed binaries. e.g. ~/.local/bin/  
echo 'python /absolute/path/to/PhysiCell-Studio/bin/studio.py $*' > studio  
chmod 775  
which studio
```

Install the Qt library dependencies:

```
sudo apt install qtbase5-dev  
pip install PyQt5
```

Test the installation with the biorobots sample project.

```
cd to wherever you have PhysiCell installed. Inside the PhysiCell folder:  
studio
```

PhysiCell Studio should open, loaded with the biorobots settings file.

Overview

This document describes the PhysiCell installation on a Debian Linux distribution. If you run on another flavor, please adjust accordingly.

- GCC
- ImageMagick, FFmpeg
- Git (optional)
- PhysiCell

} Minimum
Setup

-
- Python3 (miniconda), iPython, PhysiCell DataLoader
 - Jupyter (optional)
 - PhysiCell Studio

} Modeler
Setup

-
- Copasi

} Hackathon
Setup



Copasi (Hackathon Setup)

- The detailed instructions can be found here:
<https://copasi.org/Support/Installation/Linux/>
- `cd` to the folder where you have your manual installed programs. e.g. `~/ .local/lib`
e.g. `~/ .local/lib/`
- download copasi:
wget <https://github.com/copasi/COPASI/releases/download/Build-278/COPASI-4.40.278-Linux-64bit.sh>
- Install copasi:
`chmod 775 COPASI-4.40.278-Linux-64bit.sh`
`./COPASI-4.40.278-Linux-64bit.sh`
Thereby change the installation directory setting to where you right now are.
- Put copasi under the PATH
`cd` to the folder where you have your manual installed binaries. e.g. `~/ .local/bin/`
`ln -s /absolute/path/to/installed/CopasiSE`
`ln -s /absolute/path/to/installed/CopasiUI`

Overview

This document describes the PhysiCell installation on a Debian Linux distribution. If you run on another flavor, please adjust accordingly.

- GCC
- ImageMagick, FFmpeg
- Git (optional)
- PhysiCell

Minimum
Setup

-
- Python3 (miniconda), iPython, PhysiCell DataLoader
 - Jupyter (optional, local installation only)
 - PhysiCell Studio

Modeler
Setup

-
- Copasi

Hackathon
Setup



Funding Acknowledgements



leidos



PhysiCell Development:

- Breast Cancer Research Foundation
- Jayne Koskinas Ted Giovanis Foundation for Health and Policy
- National Cancer Institute (U01CA232137)
- National Science Foundation (1720625, 1818187)

Training materials:

- Administrative supplement to NCI U01CA232137 (Year 2)

Other Funding:

- NCI / DOE / Frederick National Lab for Cancer Research (21X126F)
- DOD / Defense Threat Reduction Agency (HDTRA12110015)
- NIH Common Fund (3OT2OD026671-01S4)